



# Upgrade from Abiquo 2.6.6 to 2.6.7

---

## 1. Description

Abiquo 2.6.7 packages upgrade the Abiquo platform servers of the Abiquo Monolithic and Abiquo Distributed installs.

Follow this documentation to upgrade every Abiquo server (Remote Services, Abiquo Server, V2V).

You do not need to upgrade KVM or LVM nodes with this release.

## 2. Prerequisites

This update is for 2.6.7. To perform a fresh install, you should install version 2.6, 2.6.1, 2.6.2, 2.6.3, 2.6.4, 2.6.5 and 2.6.6 first, and then install the 2.6.7 upgrade.

## 3. Preparation

### 3.1. Back up your system and customized elements

Before making any changes to your system, ensure that you have a complete and validated system backup. Remember to back up all customized elements, such as branding. After upgrading your system, reapply branding, and check and reapply any other customizations as necessary. See [Backup and Restore of Customization for Upgrading Abiquo](#)

### 3.2. Download the upgrade package

<http://download.abiquo.com/enterprise/updates/2.6/abiquo-upgrade-2.6.7.bin>

user: enterprise  
password: tCs3125

Package MD5:  
MD5: c97fb02cf2f7e20b256f62fbf3428fda abiquo-upgrade-2.6.7.bin

✓ **Download Command**

You can download it directly from the Abiquo Support server using the following command:

```
wget --user=enterprise --password=tCs3125 \  
http://download.abiquo.com/enterprise/updates/2.6/abiquo-upgrade-2.6.7.bin
```

## 4. Perform the upgrade

### 4.1. Remove customer access

You can prevent customers from accessing the platform by disabling all the physical machines in Abiquo (in Infrastructure view in the GUI) or using the API (setting state to HALTED).

### 4.2. Ensure all queues are empty and no tasks are in progress

On Remote Services check the status of RabbitMQ to ensure that there are no outstanding tasks

```
service rabbitmq-server status
```

This will provide the PID so you can see if it is running or not.

Secondly, check the consumers' list:

```
rabbitmqctl list_consumers
```

The result should be something like this but with more values:

```
abiquo.vsm.eventsynk ... ==true  
abiquo.tracer.traces ... ==true  
abiquo.datacenter.requests.Abiquo.virtualfactory ... ==true  
abiquo.ha.tasks ... ==true  
abiquo.am.downloads ... ==true  
abiquo.datacenter.requests.Abiquo.bpm ... ==true  
abiquo.datacenter.notifications ... ==true
```

All must be **true**.

Finally check the queues:

```
# rabbitmqctl list_queues
```

The output will be similar to this:

```
Listing queues ...
abiquo.vsm.eventsynk 0
abiquo.tracer.traces 0
abiquo.datacenter.requests.Abiquo.virtualfactory 0
abiquo.ha.tasks 0
abiquo.am.downloads 0
abiquo.datacenter.requests.Abiquo.bpm 0
abiquo.datacenter.notifications 0
...done.
```

You can check for any active V2V conversions by checking for the V2V or Mechadora processes

```
ps aux | grep v2v
ps aux | grep mechadora
```

See [Service Management](#) for details

## 4.3. Run the Abiquo Upgrade Script

Upload the upgrade package to the /root directory of the Abiquo Server, as well as the Remote Services and V2V Server.

Log in to all servers as root and run the following commands:

```
[root@localhost ~]# chmod +x abiquo-upgrade-2.6.7.bin
[root@localhost ~]# ./abiquo-upgrade-2.6.7.bin
```

### 4.3.1. Start the abiquo-tomcat service

The upgrade bundle automatically stops the abiquo-tomcat service before upgrading. On the Abiquo platform servers (Server, Remote Services), start the abiquo-tomcat service.

```
service abiquo-tomcat start
```

## 5. Verify the upgrade

On the Abiquo platform servers, check the version after the upgrade.

```
[root@localhost ~]# cat /etc/abiquo-release  
Version: 2.6.7  
Edition: Enterprise
```

## 6. Clear the browser cache

Before logging in to Abiquo after an upgrade, all users should clear the browser cache on their machines.

## 7. RPM packages upgraded in this release

The upgrade to Abiquo 2.6.7 includes the following RPM packages:

```
abiquo-release-ee-2.6.7-1.e15.noarch.rpm  
abiquo-ssm-2.6.7-1.e15.20140707_1523.noarch.rpm
```

## 8. Release Notes for Abiquo 2.6.7

### 8.1. Changes in properties in Abiquo 2.6.7

As part of Improvement 7487 to remove the hardcoded Nexenta block size value, a new **abiquo.storagemanager.nexenta.blocksize** property was introduced in Abiquo 2.6.7. If you do not set this property, the default block size of 8 KB will be used.

Abiquo supports Nexenta block sizes from 8 KB to 128 KB. Nexenta requires the block size to be a power of 2. The block size is only validated by Nexenta and it will accept values set with this property of 8, 16, 32, 64, and 128. Abiquo recommends that the block size should be at least 8 KB.

### Improvement

Key	Description
7487	Parameterize Nexenta block size value with Abiquo Configuration Property